

The image is a large, symmetrical, abstract graphic composed of the letters 'S' and 'Y' arranged in a grid-like pattern. The letters are black on a white background. The overall shape is a large, stylized 'Y' or a complex letterform. The top part is a wide horizontal bar made of 'S's, with 'Y's in the center. The sides are made of 'S's, and the bottom is a wide horizontal bar made of 'S's, with 'Y's in the center. The letters are arranged in a way that creates a sense of depth and perspective, with the 'Y's appearing to recede into the distance.

```

SSSSSSSS YY YY SSSSSSSS SSSSSSSS NN NN DDDDDDD JJ BBBBBBB CCCCCC
SSSSSSSS YY YY SSSSSSSS SSSSSSSS NN NN DDDDDDD JJ BBBBBBB CCCCCC
SS SS YY YY SS SS SS SS NN NN DD DD JJ BB BB CC
SS SS YY YY SS SS SS SS NN NN DD DD JJ BB BB CC
SS SSSSSS YY YY SSSSSS SSSSSS NN NN DD DD JJ BBBBBBB CC
SS SSSSSS YY YY SSSSSS SSSSSS NN NN DD DD JJ BBBBBBB CC
SS SS YY YY SS SS SS SS NN NN DD DD JJ BB BB CC
SSSSSSSS YY YY SSSSSSSS SSSSSSSS NN NN DD DDDDDDD JJJJJJ BBBBBBB CCCCCC
SSSSSSSS YY YY SSSSSSSS SSSSSSSS NN NN DDDDDDD JJJJJJ BBBBBBB CCCCCC

```

```

LL LL LL LL LL LL LL LL LL LL LL LLLLLLLLLL LLLLLLLLLL
IIIIII IIIII IIIII II II II II II II II II IIIII IIIII
SS SS SS SS SSSSSS SSSSSS SS SS SS SS SSSSSS SSSSSS

```

(2) 100  
(5) 268  
(16) 1024

DATA DEFINITIONS  
EX\$SNDJBC - Send message to job controller  
EX\$JBCRSP - Store response from job controller



```
0000 1      .TITLE SYSSNDJBC - SEND MESSAGE TO JOB CONTROLLER
0000 2      .IDENT 'V04-000'
0000 3
0000 4
0000 5 *****
0000 6 *****
0000 7      COPYRIGHT (c) 1978, 1980, 1982, 1984 BY
0000 8      DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.
0000 9      ALL RIGHTS RESERVED.
0000 10
0000 11      THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED
0000 12      ONLY IN ACCORDANCE WITH THE TERMS OF SUCH LICENSE AND WITH THE
0000 13      INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR ANY OTHER
0000 14      COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY
0000 15      OTHER PERSON. NO TITLE TO AND OWNERSHIP OF THE SOFTWARE IS HEREBY
0000 16      TRANSFERRED.
0000 17
0000 18      THE INFORMATION IN THIS SOFTWARE IS SUBJECT TO CHANGE WITHOUT NOTICE
0000 19      AND SHOULD NOT BE CONSTRUED AS A COMMITMENT BY DIGITAL EQUIPMENT
0000 20      CORPORATION.
0000 21
0000 22      DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE OR RELIABILITY OF ITS
0000 23      SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.
0000 24
0000 25 *****
0000 26 *****
0000 27
0000 28
0000 29      ++
0000 30      FACILITY:
0000 31      System services.
0000 32
0000 33      ABSTRACT:
0000 34      This module implements the Send to Job Controller ($SNDJBC) and the
0000 35      Get Queue Information ($GETQUI) system services.
0000 36
0000 37      AUTHOR: M. Jack, CREATION DATE: 29-Aug-1982
0000 38
0000 39      MODIFIED BY:
0000 40
0000 41      V03-011 JAK0218      J A Krycka      10-Jul-1984
0000 42      Update tables to support new $SNDJBC and $GETQUI item codes.
0000 43
0000 44      V03-010 JAK0203      J A Krycka      17-Apr-1984
0000 45      Update tables to support new $SNDJBC item codes.
0000 46
0000 47      V03-009 TMK0001      Todd M. Katz      04-Apr-1984
0000 48      Re-write the action routine TRANSLATE_OBJECT to:
0000 49
0000 50      1. Replace the recursive $TRNLOGs with $TRNLNMs.
0000 51
0000 52      2. Eliminate the code that removes tabs, blanks, and null
0000 53      characters from names before attempting to translate them.
0000 54      Logical names should be handled in a systematic fashion
0000 55      throughout the system, and nobody else fiddles with them in
0000 56      such a fashion. However, after the recursive translations
0000 57      complete, at this time format the final translation according
```

0000 58 :  
0000 59 :  
0000 60 :  
0000 61 :  
0000 62 :  
0000 63 :  
0000 64 :  
0000 65 :  
0000 66 :  
0000 67 :  
0000 68 :  
0000 69 :  
0000 70 :  
0000 71 :  
0000 72 :  
0000 73 :  
0000 74 :  
0000 75 :  
0000 76 :  
0000 77 :  
0000 78 :  
0000 79 :  
0000 80 :  
0000 81 :  
0000 82 :  
0000 83 :  
0000 84 :  
0000 85 :  
0000 86 :  
0000 87 :  
0000 88 :  
0000 89 :  
0000 90 :  
0000 91 :  
0000 92 :  
0000 93 :  
0000 94 :  
0000 95 :  
0000 96 :  
0000 97 :  
0000 98 :--

to the syntax expected for queue names. This involves removing tabs, null characters, and spaces from the final translation, and then upcasing it. This upcasing is done by means of the DEC multi-national character upcasing table.

3. Eliminate the code that upcases names before their translation because the \$TRNLNMs will be done case-insensitive.

4. Micro-optimize the action routine.

V03-008 ACG0354 Andrew C. Goldstein, 13-Sep-1983  
Change delete protection check to use alternate access rather than access-granted.

V03-007 MLJ0118 Martin L. Jack, 22-Aug-1983  
Guard against overlong resultant filename. Update tables and limits for new \$GETQUI and \$SNDJBC items.

V03-006 MLJ0115 Martin L. Jack, 30-Jul-1983  
Changes for job controller baselevel.

V03-005 MLJ0114 Martin L. Jack, 23-Jun-1983  
Add support for \$GETQUI and for new \$SNDJBC items.

V03-004 MLJ0112 Martin L. Jack, 28-Apr-1983  
Update tables and limits for new items corresponding to job controller baselevel.

V03-003 CWH1002 CW Hobbs 24-Feb-1983  
Send extended pid and owner fields to the job controller.

V03-002 MLJ0106 Martin L. Jack, 1-Mar-1983  
Update tables and limits for new items corresponding to job controller baselevel.

V03-001 MLJ0103 Martin L. Jack, 7-Jan-1983  
Update tables and limits for new items corresponding to job controller baselevel.



```
0000 100      .SBTTL DATA DEFINITIONS
0000 101
0000 102 :
0000 103 : EXTERNAL SYMBOLS:
0000 104 :
0000 105 :
0000 106      $ACBDEF      ; Define AST control block offsets
0000 107      $ACMDEF      ; Define accounting manager offsets
0000 108      $ARMDEF      ; Define access rights mask
0000 109      $ATRDEF      ; Define ACP attribute codes
0000 110      $FABDEF      ; Define RMS file attributes block offsets
0000 111      $FATDEF      ; Define RMS file attribute area offsets
0000 112      $FIBDEF      ; Define file information block offsets
0000 113      $IODEF       ; Define I/O function codes
0000 114      $LNMDEF      ; Define logical name system service symbols
0000 115      $MSGDEF      ; Define mailbox message types
0000 116      $NAMDEF      ; Define RMS name block offsets
0000 117      $PCBDEF      ; Define process control block offsets
0000 118      $PHDDEF      ; Define process header offsets
0000 119      $PSLDEF      ; Define processor status longword offsets
0000 120      $QUIDEF      ; Define $GETQUI function and item codes
0000 121      $$JCDEF      ; Define $$SNDJBC function and item codes
0000 122      $$SDEF       ; Define system status codes
0000 123
0000 124 :
0000 125 : LOCAL SYMBOLS:
0000 126 :
0000 127 : Extension to AST control block. These definitions are also known to JOBCTL.
0000 128 :
0000 129
0000001C 0000 130      $DEFINI ACB
0000 131      . = ACB$L KAST+4      ; Position to end
0000 132 $DEF ACB_L_IMGCNT .BLKL 1 ; Image counter
0000 133 $DEF ACB_L_EFN .BLKL 1 ; Event flag number
0000 134 $DEF ACB_L_IOSB .BLKL 1 ; IOSB address
0000 135 $DEF ACB_L_STATUS .BLKL 1 ; Status for IOSB
0000 136 $DEF ACB_W_ITEMCOUNT .BLKW 1 ; Count of data items
0000 137 $DEF ACB_B_ITEMS .BLKB 0 ; Base of item descriptors
0000 138 $DEFEND ACB
0000 139
0000 140 :
0000 141 : Argument list offsets (based on AP).
0000 142 :
0000 143
00000004 0000 144 EFN= 4 ; Event flag number
00000008 0000 145 FUNC= 8 ; Function code
0000000C 0000 146 NULARG= 12 ; Reserved argument
00000010 0000 147 ITMLST= 16 ; Address of item descriptor list
00000014 0000 148 IOSB= 20 ; Address of I/O status block
00000018 0000 149 ASTADR= 24 ; Address of AST routine
0000001C 0000 150 ASTPRM= 28 ; AST parameter
0000 151
0000 152 :
0000 153 : Data table offsets (based on R11).
0000 154 :
0000 155
00000000 0000 156 MSG_CODE= 0 ; Message function code
```

```
00000004 0000 157 MAX_FUNC=      4      ; Highest function code minus one
00000008 0000 158 MAX_ITEM=      8      ; Highest item code minus one
0000000C 0000 159 BOOC_ITEM=     12      ; Pointer to boolean item table
00000010 0000 160 OUTPUT_ITEM=    16      ; Pointer to output item table
00000014 0000 161 SPECIAC_TABLE=  20      ; Pointer to special handling table
          0000 162
          0000 163
          0000 164 ; Fixed work area offsets (above FP).
          0000 165
          0000 166
FFFFF8FC 0000 167 FILE_ID=     -4      ; Pointer to file identification item
FFFFF8F8 0000 168 FLAGS=       -8      ; Pointer to miscellaneous status flags
00000000 0000 169 DELETE_FLAG=   0      ; SJCS_DELETE_FILE seen
          0000 170
          0000 171
          0000 172 ; Miscellaneous definitions.
          0000 173
          0000 174
0000005A 0000 175 FIXED_AREA=   ACMSQ_SYSTIME+8 + 22 ; Size of fixed area of message
```



```
0000 177
0000 178 :
0000 179 : LOCAL STORAGE:
0000 180 :
0000 181 : This table is indexed by item code (normalized to zero origin). It
0000 182 : identifies items classified as Boolean.
0000 183 :
0000 184 :
00000000 185 .PSECT Y$EXEPAGED
0000 186 SNDJBC_BOOL_ITEM:
99EAA198 0000 187 .LONG ^B10011001111010101010000110011000
B7005D3B 0004 188 .LONG ^B10110111000000000101110100111011
EB751BDF 0008 189 .LONG ^B11101011011101010001101111011111
C03B5DFC 000C 190 .LONG ^B11000000001110110101110111111100
0A9F3F09 0010 191 .LONG ^B00001010100111110011111100001001
0000001E 0014 192 .LONG ^B00000000000000000000000000001110
00000000 0018 193 .LONG ^B00000000000000000000000000000000
00000000 001C 194 .LONG ^B00000000000000000000000000000000
0020 195 GETQUI_BOOL_ITEM:
00000000 0020 196 .LONG ^B00000000000000000000000000000000
00000000 0024 197 .LONG ^B00000000000000000000000000000000
00300000 0028 198 .LONG ^B00000000000110000000000000000000
00000000 002C 199 .LONG ^B00000000000000000000000000000000
00000000 0030 200 .LONG ^B00000000000000000000000000000000
00000000 0034 201 .LONG ^B00000000000000000000000000000000
00000000 0038 202 .LONG ^B00000000000000000000000000000000
00000000 003C 203 .LONG ^B00000000000000000000000000000000
0040 204 :
0040 205 :
0040 206 : This table is indexed by item code (normalized to zero origin). It
0040 207 : identifies items classified as output.
0040 208 :
0040 209 :
0040 210 SNDJBC_OUTPUT_ITEM:
40000400 0040 211 .LONG ^B0100000000000000000000001000000000
00000000 0044 212 .LONG ^B00000000000000000000000000000000
00800000 0048 213 .LONG ^B00000000100000000000000000000000
00000000 004C 214 .LONG ^B00000000000000000000000000000000
00000000 0050 215 .LONG ^B00000000000000000000000000000000
00000600 0054 216 .LONG ^B0000000000000000000000011000000000
00000000 0058 217 .LONG ^B00000000000000000000000000000000
00000000 005C 218 .LONG ^B00000000000000000000000000000000
0060 219 GETQUI_OUTPUT_ITEM:
FFFFFFFF 0060 220 .LONG ^B11111111111111111111111111111111
FFFFFFFF 0064 221 .LONG ^B11111111111111111111111111111111
3F0FC7FF 0068 222 .LONG ^B00111111000011111100011111111111
00000000 006C 223 .LONG ^B00000000000000000000000000000000
00000000 0070 224 .LONG ^B00000000000000000000000000000000
00000000 0074 225 .LONG ^B00000000000000000000000000000000
00000000 0078 226 .LONG ^B00000000000000000000000000000000
00000000 007C 227 .LONG ^B00000000000000000000000000000000
0080 228 :
0080 229 :
0080 230 : This table identifies item codes that require special translation and the
0080 231 : routine that performs the translation.
0080 232 :
0080 233 :
```



```
000C 0080 234 SNDJBC_SPECIAL_TABLE:
000004B0' 0080 235 .WORD SJCS_CHARACTERISTIC_NAME
001A 0082 236 .LONG TRANSLATE_OBJECT
000004B0' 0086 237 .WORD SJCS_DESTINATION_QUEUE
000004B0' 0088 238 .LONG TRANSLATE_OBJECT
0027 008C 239 .WORD SJCS_FILE_IDENTIFICATION
00000369' 008E 240 .LONG FILE_IDENTIFICATION
002A 0092 241 .WORD SJCS_FILE_SPECIFICATION
000002F1' 0094 242 .LONG FILE_SPECIFICATION
0036 0098 243 .WORD SJCS_FORM_NAME
000004B0' 009A 244 .LONG TRANSLATE_OBJECT
0046 009E 245 .WORD SJCS_GENERIC_TARGET
000004B0' 00A0 246 .LONG TRANSLATE_OBJECT
0061 00A4 247 .WORD SJCS_LOG_QUEUE
000004B0' 00A6 248 .LONG TRANSLATE_OBJECT
0086 00AA 249 .WORD SJCS_QUEUE
000004B0' 00AC 250 .LONG TRANSLATE_OBJECT
0000 00B0 251 .WORD 0
004D 00B2 252 GETQUI_SPECIAL_TABLE:
000004B0' 00B2 253 .WORD QUI$SEARCH_NAME
0000 00B4 254 .LONG TRANSLATE_OBJECT
0000 00B8 255 .WORD 0
00BA 256
00BA 257
00BA 258
00BA 259
00BA 260
00BA 261
00BA 262
02000000 00BA 263
00BE 264
00BE 265
00BE 266
00CC
```

## GETQUI\_SPECIAL\_TABLE:

```
.WORD QUI$SEARCH_NAME
.LONG TRANSLATE_OBJECT
.WORD 0
```

: The following values are needed as arguments to the \$TRNLNMs performed by  
: the action routine TRANSLATE\_OBJECT.

## TRNLNM\_ATTR:

```
.LONG LNMSM_CASE_BLIND
```

: Optional attributes for \$TRNLNMs  
: Translations are done case-insensitive

## TRNLNM\_TABLE:

```
.ASCID /LNMSFILE_DEV/
```

: Tables in which to do the translations

```
49 46 24 4D 4E 4C 000000C6'010E0000'
56 45 44 5F 45 4C 00CC
```

```
00D2 268 .SBTTL EXE$SNDJBC - Send message to job controller
00D2 269
00D2 270 :++
00D2 271
00D2 272 EXE$SNDJBC - SEND MESSAGE TO JOB CONTROLLER
00D2 273 EXE$GETQUI - GET QUEUE INFORMATION
00D2 274
00D2 275 FUNCTIONAL DESCRIPTION:
00D2 276
00D2 277 This routine provides the send to job controller and get queue
00D2 278 information system services. The action is to build a message from the
00D2 279 user's input data and send it to the job controller mailbox. At request
00D2 280 completion, the job controller queues a special kernel AST to routine
00D2 281 EXE$JBCRSP to return status to this process.
00D2 282
00D2 283 INPUTS:
00D2 284 EFN(AP) = Number of the event flag to set at request completion
00D2 285 FUNC(AP) = Function code
00D2 286 NULARG(AP) = Reserved argument, must be zero
00D2 287 ITMLST(AP) = Address of a list of item descriptors
00D2 288 IOSB(AP) = Address of a quadword to receive completion status
00D2 289 ASTADR(AP) = Address of an AST routine to be called at request
00D2 290 completion
00D2 291 ASTPRM(AP) = Longword AST parameter
00D2 292
00D2 293 OUTPUTS:
00D2 294 R0 = Status of the operation
00D2 295
00D2 296 STATUS CODES RETURNED:
00D2 297 SSS_NORMAL Successful operation
00D2 298
00D2 299 SSS_ACCVIO Unable to write IOSB, read ITMLST, read or write item
00D2 300 buffer, write return length buffer
00D2 301 SSS_BADPARAM Invalid FUNC, nonzero NULARG, invalid item code,
00D2 302 invalid zero or nonzero field in item descriptor
00D2 303 SSS_DEVOFFLINE No job controller
00D2 304 SSS_EXASTLM Exceeded ASTLM quota
00D2 305 SSS_ILLEFC Illegal event flag number
00D2 306 SSS_INSMEM Insufficient system memory to complete request
00D2 307 SSS_MBFULL Job controller mailbox full
00D2 308 SSS_MBTOSML Message too large for job controller mailbox
00D2 309 SSS_UNASEFC Unassociated event flag cluster
00D2 310 :--
00D2 311
00D2 312 GETQUI_DATA:
00000010 00D2 313 .LONG MSG$_GETQUI : Message function code
00000008 00D6 314 .LONG QUI$_RESERVED_FUNC_2-1 : Highest function code minus one
0000005D 00DA 315 .LONG QUI$_RESERVED_OUTPUT_6-1 : Highest item code minus one
00000020 00DE 316 .LONG GETQUI_BOOL_ITEM : Pointer to boolean item table
00000060 00E2 317 .LONG GETQUI_OUTPUT_ITEM : Pointer to output item table
000000B2 00E6 318 .LONG GETQUI_SPECIAL_TABLE : Pointer to special handling table
00EA 319
00EA 320 SNDJBC_DATA:
0000000F 00EA 321 .LONG MSG$_SNDJBC : Message function code
0000001F 00EE 322 .LONG SJCS$_RESERVED_FUNC_2-1 : Highest function code minus one
000000AA 00F2 323 .LONG SJCS$_RESERVED_OUTPUT_2-1 : Highest item code minus one
00000000 00F6 324 .LONG SNDJBC_BOOL_ITEM : Pointer to boolean item table
```

```
00000040' 00FA 325      .LONG  SNDJBC_OUTPUT_ITEM      ; Pointer to output item table
00000080' 00FE 326      .LONG  SNDJBC_SPECIAL_TABLE    ; Pointer to special handling table
0102 327
0102 328      .ENABL  LSB
0102 329
0102 330 ACCVIO:
50  0C  D0 0102 331      MOVL   #SS$ _ACCVIO,R0      ; Set access violation status
   0A  11 0103 332      BRB    10$
0107 333
0107 334 BADPARAM:
50  14  D0 0107 335      MOVL   #SS$ _BADPARAM,R0    ; Set bad parameter status
   05  11 010A 336      BRB    10$
010C 337
010C 338 INSMEM:
50  0124 8F 3C 010C 339      MOVZWL  #SS$ _INSMEM,R0    ; Set insufficient memory status
   0472 31 0111 340      10$:  BRW    ERROR
0114 341
0114 342
0114 343 EXE$GETQUI::      ; Get queue information
   OFFC 0114 344      .WORD   ^M<R2,R3,R4,R5,R6,R7,R8,R9,R10,R11>
5B  B9  AF  9E 0116 345      MOVAB   GETQUI_DATA,R11    ; Point to $GETQUI data table
   06  11 011A 346      BRB    20$      ; Join common code
011C 347
011C 348
011C 349 EXE$SNDJBC::    ; Send to job controller
5B  C9  AF  9E 011C 350      .WORD   ^M<R2,R3,R4,R5,R6,R7,R8,R9,R10,R11>
   011E 351      MOVAB   SNDJBC_DATA,R11    ; Point to $SNDJBC data table
0122 352
0122 353      ;
0122 354      ; Point to lowest usable stack address.
0122 355      ;
0122 356
0122 357 20$:  CLRQ    -(SP)      ; Allocate fixed work area
50  50  02  7E 7C 0124 358      MOVPSL  R0      ; Get PSL
   18  DC 0126 359      EXTZV   #PSL$V_CURMOD,#PSL$S_CURMOD,R0,R0 ; Get current mode
00000000'EF40 50 0000008E 8F C1 012B 360      ADDL3   #FIXED_AREA+52, - ; Allow slop for fixed message area plus
   5A 0137 361      CTL$AL_STACKLIM[R0], - ; 52 bytes for $CMKRNL frame and
0138 362      R10      ; parameters
0138 363
0138 364      ;
0138 365      ; Check for and clear I/O status block.
0138 366      ;
0138 367
0138 368      MOVL   IOSB(AP),R0      ; Get IOSB address
50  14  AC  D0 0138 369      BEQL   30$      ; Branch if none
   08  13 013C 370      IFNOWRT #8,(R0),ACCVIO    ; Check write access to IOSB
   60  7C 0144 371      CLRQ    (R0)      ; Clear IOSB
0146 372
0146 373      ;
0146 374      ; Validate function code.
0146 375      ;
0146 376
0146 377 30$:  SUBL3   #1,FUNC(AP),R2      ; Get function code and subtract out
52  08  AC  01  C3 0146 378      ; smallest value to get zero origin
   04  AB  52  D1 014B 379      CMLPL  R2,MAX_FUNC(R11)    ; Check against largest value
   B6  1A 014F 380      BGTRU   BADPARAM      ; Branch if invalid value
0151 381
```



```
0151 382 :  
0151 383 : Validate unused argument (must be zero).  
0151 384 :  
0151 385 :  
OC AC DS 0151 386 TSTL NULARG(AP) : Unused argument zero?  
B1 12 0154 387 BNEQ BADPARAM : Branch if not zero  
0156 388 :  
0156 389 :  
0156 390 : Process the item list to build the job controller message. During this loop:  
0156 391 :  
0156 392 : R5 = buffer size  
0156 393 : R6 = item code  
0156 394 : R7 = buffer address  
0156 395 : R8 = return length address  
0156 396 : R9 = pointer to item list  
0156 397 : R10 = pointer to lowest available stack address  
0156 398 : R11 = pointer to service-specific data area  
0156 399 :  
59 10 AC D0 0156 400 :  
OE 13 015A 401 MOVL ITMLST(AP),R9 : Get item descriptor list address  
015C 402 BEQL 40$ : Branch if no item list  
55 89 3C 0162 403 IFNORD #4,(R9),90$ : Check read access to first longword  
56 89 3C 0165 404 ITEM: MOVZWL (R9)+,R5 : Get buffer size value  
03 12 0168 405 MOVZWL (R9)+,R6 : Get item code value  
00B0 31 016A 406 BNEQ 50$ : Branch if nonzero, list not ended  
52 56 01 016D 407 40$: BRW FINISH_MESSAGE : Branch if zero, list ended  
C3 0171 408 50$: SUBL3 #1,R6,R2 : Subtract out smallest value to get  
08 AB 52 D1 0171 409 : zero origin  
59 1A 0175 410 CMPL R2,MAX_ITEM(R11) : Check against largest value  
0177 411 BGTRU 100$ : Branch if invalid value  
017D 412 IFNORD #12,(R9),90$ : Check read access to second and third  
017D 413 : longwords of this item and first  
017D 414 : longword of next item  
57 89 7D 017D 415 MOVQ (R9)+,R7 : Get buffer address and return length  
0180 416 : address  
0180 417 :  
0180 418 : Boolean item. Store the item code.  
0180 419 :  
0180 420 :  
17 OC BB 52 E1 0180 421 BBC R2,@BOOL_ITEM(R11),60$ : Branch if not boolean item  
50 SE 02 C3 0185 422 SUBL3 #2,SP,R0 : Get lowest address that will be used  
5A 50 D1 0189 423 CMPL R0,R10 : Compare against that available  
45 1F 018C 424 BLSSU 110$ : Branch if space exceeded  
7E 56 B0 018E 425 MOVW R6,-(SP) : Store item code  
18 56 B1 0191 426 CMPW R6,#SJCS_DELETE_FILE : Check for file deletion  
CC 12 0194 427 BNEQ ITEM :  
FB AD 01 88 0196 428 BISB #1@DELETE_FLAG,FLAGS(FP) : Note file deletion for postprocessing  
C6 11 019A 429 BRB ITEM : Branch to process next item  
019C 430 :  
019C 431 :  
019C 432 : Input or output item. Set up to call EXESPROBEx.  
019C 433 :  
019C 434 :  
50 57 D0 019C 435 60$: MOVL R7,R0 : R0 = buffer address  
51 55 D0 019F 436 MOVL R5,R1 : R1 = buffer length  
53 D4 01A2 437 CLRL R3 : R3 = probe against previous mode  
55 DD 01A4 438 PUSHL R5 : Save R5 across call
```

```
01A6 439
01A6 440
01A6 441 : Input item. Ensure that the buffer is accessible.
01A6 442 :
01A6 443
47 10 BB 52 E0 01A6 444 BBS R2,@OUTPUT_ITEM(R11),120$ : Branch if output item
00000000'EF 16 01AB 445 JSB EXESPROBER : Probe read access to buffer
55 BED0 01B1 446 POPL R5 : Restore R5
16 50 E9 01B4 447 BLBC R0,90$ : Branch if no access
01B7 448
01B7 449
01B7 450 : Test for items that receive special translation.
01B7 451 :
01B7 452
50 14 AB D0 01B7 453 MOVL SPECIAL_TABLE(R11),R0 : Point to special handling table
51 60 3C 01BB 454 70$: MOVZWL (R0),R1 : Pick up item code and test if ended
16 13 01BE 455 BEQL INPUT_ITEM : Branch if ended
51 56 D1 01C0 456 CMPL R6,R1 : Correct item code?
03 12 01C3 457 BNEQ 80$ : Branch if not
02 B0 17 01C5 458 JMP @2(R0) : Jump to processing routine
50 06 C0 01C8 459 80$: ADDL2 #6,R0 : Increment to next table entry
EE 11 01CB 460 BRB 70$ : Loop to compare next
01CD 461
01CD 462
01CD 463 : Helper branches.
01CD 464 :
01CD 465
FF32 31 01CD 466 90$: BRW ACCVIO
FF34 31 01D0 467 100$: BRW BADPARAM
FF36 31 01D3 468 110$: BRW INSFMEM
01D6 469
01D6 470
01D6 471 : Ordinary input item. Store the item code, buffer length, and contents.
01D6 472 :
01D6 473
01D6 474 INPUT_ITEM:
50 SE 55 C3 01D6 475 SUBL3 R5,SP,R0 : Get lowest address that will be used
50 04 C2 01DA 476 SUBL2 #4,R0 :
5A 50 D1 01DD 477 CMPL R0,R10 : Compare against that available
F1 1F 01E0 478 BLSSU 110$ : Branch if space exceeded
SE 50 D0 01E2 479 MOVL R0,SP : Allocate the space
80 56 B0 01E5 480 MOVW R6,(R0)+ : Store item code
80 55 B0 01E8 481 MOVW R5,(R0)+ : Store item length
60 67 55 B0 01EB 482 MOVCL R5,(R7),(R0) : Store item value
FF70 31 01EF 483 BRW ITEM : Branch to process next item
01F2 484
01F2 485
01F2 486 : Output item. Ensure that the buffer, and return length if specified, are
01F2 487 : accessible, and store the item code, buffer length, buffer address, and return
01F2 488 : length address.
01F2 489 :
01F2 490
00000000'EF 16 01F2 491 120$: JSB EXESPROBER : Probe write access to buffer
55 BED0 01FB 492 POPL R5 : Restore R5
CF 50 E9 01FB 493 BLBC R0,90$ : Branch if no access
58 D5 01FE 494 TSTL R8 : Test if return length specified
06 13 0200 495 BEQL 130$ : Branch if not specified
```

```

50  5E  0C  C3  0202  496  IFNOWRT #2 (R8), 90$      : Probe write access to length word
    5A  50  D1  0208  497  130$:  SUBL3  #12, SP, R0      : Get lowest address that will be used
    5A  C2  1F  020C  498  : CMPL  R0, R10      : Compare against that available
    7E  57  7D  020F  499  : BLSSU  110$      : Branch if space exceeded
    7E  55  B0  0211  500  : MOVQ   R7, -(SP)      : Store item buffer addresses
    7E  56  B0  0214  501  : MOVW   R5, -(SP)      : Store item length
    7E  56  B0  0217  502  : MOVW   R6, -(SP)      : Store item code
    FF45 31  021A  503  : BRW    ITEM      : Branch to process next item
    021D  504  :
    021D  505  :
    021D  506  : To here when all items have been processed. Do necessary postprocessing
    021D  507  : and finish the message.
    021D  508  :
    021D  509  :
    021D  510  FINISH_MESSAGE:
    5A  FC AD  D0  021D  511  : MOVL   FILE_ID(FP), R10      : Get file ID item, if any
    03  13  13  0221  512  : BEQL   140$      : Branch if none
    017C 30  0223  513  : BSBW   POSTPROCESS_FID      : Deal with it
    0226  514  :
    0226  515  : Build the message header.
    0226  516  :
    0226  517  :
    0226  518  :
    56  00000000'9F  D0  0226  519  140$:  MOVL   @#CTL$GL_PCB, R6      : Get PCB address
    57  00000000'9F  D0  022D  520  : MOVL   @#CTL$GL_PHD, R7      : Get PHD address
    7E  08 AC  B0  0234  521  : MOVW   FUNC(AP), -(SP)      : Store function code
    7E  18 AC  7D  0238  522  : MOVQ   ASTADR(AP), -(SP)      : Store AST address and parameter
    7E  14 AC  DD  023C  523  : PUSHL  IOSB(AP)      : Store IOSB address
    7E  04 AC  9A  023F  524  : MOVZBL EFN(AP), -(SP)      : Store event flag number
    00F4 C7  DD  0243  525  : PUSHL  PHD$$_IMGcnt(R7)      : Store image counter
    5E  08  C2  0247  526  : SUBL2  #8, SP      : Make space for system time
    6E  00000000'EF  7D  024A  527  150$:  MOVQ   EXESGQ_SYSTIME, (SP)      : Store current time
    6E  00000000'EF  D1  0251  528  : CMPL   EXESGQ_SYSTIME, (SP)      : Verify that value acquired was not
    04 AE  00000004'EF  D1  025A  529  : BNEQ   150$      : being modified at the same time
    04 AE  00000004'EF  D1  025A  530  : CMPL   EXESGQ_SYSTIME+4, 4(SP)      : and store it again if it changed
    04 AE  00000004'EF  D1  025A  530  : BNEQ   150$      :
    7E  44 A6  7D  0264  532  : MOVQ   PCB$$_TERMINAL(R6), -(SP)      : Store terminal name
    7E  68 A6  DD  0268  533  : PUSHL  PCB$$_EOWNER(R6)      : Store extended owner process ID
    7E  24 A6  DD  026B  534  : PUSHL  PCB$$_STS(R6)      : Store process status
    7E  64 A6  DD  026E  535  : PUSHL  PCB$$_EPID(R6)      : Store extended process ID
    7E  7E  B4  0271  536  : CLRW   -(SP)      : Clear spare word
    50  50  02  50  DC  0273  537  : MOVPSL R0      : Get PSL
    50  7E  16  50  EF  0275  538  : EXTZV  #PSL$$_PRVMOD, #PSL$$_PRVMOD, R0, R0 : Get previous mode
    7E  1F  7E  50  90  027A  539  : MOVB   R0, -(SP)      : Store requester's mode
    7E  1F  2F A6  83  027D  540  : SUBB3  PCB$$_PRIB(R6), #31, -(SP)      : Store base priority
    6E  00000000'9F  14  C2  0282  541  : SUBL2  #20, SP      : Allocate space for next field
    6E  00000000'9F  14  28  0285  542  : MOVCS  #20, @#CTL$$_USERNAME, (SP)      : Store username and account name
    00BC C6  DD  028D  543  : PUSHL  PCB$$_UIC(R6)      : Store UIC
    7E  67  7D  0291  544  : MOVQ   PHD$$_PRIVMSK(R7), -(SP)      : Store privileges
    7E  6B  3C  0294  545  : MOVZWL MSG_CODE(R11), -(SP)      : Store message type, clear mailbox
    0297  546  :
    0297  547  :
    0297  548  : Finished building the message. Push the address of the service argument
    0297  549  : list, and the address and length of the message, and enter kernel mode to
    0297  550  : complete argument list processing and write the message.
    0297  551  :
    0297  552  :
```



```
7E  5D  5E  DD  0297  553      PUSHL  SP                ; Push address of message
    6E  6E  C3  0299  554      SUBL3   (SP),FP,-(SP)        ; Push length of message
    08  C2  029D  555      SUBL     #8,(SP)                ; Deduct fixed work area
    5C  DD  02A0  556      PUSHL  AP                ; Push service argument list
    01 50  E9  02A2  557      $CMKRNLS B^170$,(SP)          ; Finish in kernel mode
    04  04  02AE  558      BLBC    RO,160$              ; Branch if error
    02D1 31  02B1  559      RET                     ; Return
    02B2  560 160$: BRW      ERROR                      ; Helper branch
    02B3  561
    02B5  562
    02B5  563      ; Kernel mode routine to finish processing.
    02B5  564
    02B5  565
    007C 02B5  566 170$: .WORD  *M<R2,R3,R4,R5,R6>        ; Entry mask
    02B7  567
    02B7  568
    02B7  569      ; Get parameter list address and PCB address.
    02B7  570
    02B7  571
    54  00000000'9F  D0  02B7  572      MOVL    @#CTL$GL_PCB,R4        ; Get PCB address
    56  8C  D0  02BE  573      MOVL    (AP)+,R6              ; Get service parameter list address
    02C1  574
    02C1  575
    02C1  576      ; Clear event flag.
    02C1  577
    02C1  578
    53  04  A6  9A  02C1  579      MOVZBL  EFN(R6),R3          ; Get event flag number
    00000000'EF  16  02C5  580      JSB     SCH$CLREF          ; Clear this event flag
    22 50  E9  02CB  581      BLBC    RO,190$              ; Return on errors
    02CE  582
    02CE  583
    02CE  584      ; Check and charge AST quota.
    02CE  585
    02CE  586
    18  A6  D5  02CE  587      TSTL     ASTADR(R6)          ; AST routine specified?
    0D  13  02D1  588      BEQL     180$                    ; Branch if none
    50  2A04 8F  3C  02D3  589      MOVZWL  #SS$ EXASTLM,R0      ; Assume AST quota exceeded status
    38  A4  B5  02D8  590      TSTW     PCB$W_ASTCNT(R4)      ; Test for quota exceeded
    13  15  02DB  591      BLEQ     190$                    ; Branch if exceeded
    38  A4  B7  02DD  592      DECW     PCB$W_ASTCNT(R4)      ; Charge AST quota
    02E0  593
    02E0  594
    02E0  595      ; Send the message.
    02E0  596
    02E0  597
    55  53  6C  7D  02E0  598 180$: MOVQ     (AP),R3          ; R3 = size, R4 = address of message
    00000000'EF  9E  02E3  599      MOVAB   SYSS$GL_JOBCTLMB,R5  ; R5 = mailbox UCB address
    00000000'EF  16  02EA  600      JSB     EXE$SENDMSG        ; Send message
    04  04  02F0  601 190$: RET                     ; Return
    02F1  602      .DSABL  LSB
```

```
02F1 604
02F1 605
02F1 606 : Stack work area offsets for next routine.
02F1 607
02F1 608
00000000 02F1 609 FWA_DVI= 0 : DVI
00000010 02F1 610 FWA_FID= 16 : FID
00000016 02F1 611 FWA_DID= 22 : DID
0000001C 02F1 612 FWA_FILE_SIZE= 28 : File size in blocks
02F1 613 : (spare longword)
00000024 02F1 614 FWA_FILE_SPEC= 36 : File specification
00000124 02F1 615 FWA_RECATTR= 292 : Record attributes
00000144 02F1 616 FWA_CHAN= 324 : Channel assigned to device
00000148 02F1 617 FWA_IOSB= 328 : I/O status block
02F1 618
0000001C 02F1 619 FWA_FAB= 28 : FAB block
0000006C 02F1 620 FWA_NAM= FWA_FAB + FAB$C_BLN : NAM block
000000CC 02F1 621 FWA_ESA= FWA_NAM + NAM$C_BLN : Expanded string
000001CB 02F1 622 FWA_SIZE= FWA_ESA + NAM$C_MAXRSS : Length of area
02F1 623
00000024 02F1 624 FWA_DVI_DESC= 36 : Descriptor for device name
02F1 625
00000024 02F1 626 FWA_FIB_DESC= 36 : Descriptor for FIB
0000002C 02F1 627 FWA_FIB= 44 : File information block
0000006C 02F1 628 FWA_ATRLIST= FWA_FIB+FIB$C_LENGTH : Attribute list
02F1 629
02F1 630 .ENABL LSB
02F1 631 FILE_SPECIFICATION: : Translate SJC$_FILE_SPECIFICATION
02F1 632
02F1 633 :
02F1 634 : R5 = buffer size
02F1 635 : R6 = item code
02F1 636 : R7 = buffer address
02F1 637 : R10 = pointer to lowest available stack address
02F1 638
02F1 639 : Check that the parameter is the correct length.
02F1 640 :
02F1 641
FC AD DS 02F1 642 TSTL FILE_ID(FP) : See if there is already a filespec
00FF 8F 6D 12 02F4 643 BNEQ 20$ : Branch if so
55 B1 02F6 644 CMPW R5,#255 : Ensure no longer than 255 bytes
66 1A 02FB 645 BGTRU 20$ : Branch if incorrect
02FD 646
02FD 647 :
02FD 648 : Check for sufficient space to allocate the work area, and do so.
02FD 649 :
02FD 650
50 FE35 CE 9E 02FD 651 MOVAB -FWA_SIZE(SP),R0 : Get lowest address that will be used
SA 50 D1 0302 652 CMPL R0,R10 : Compare against that available
5F 1F 0305 653 BLSSU 30$ : Branch if space exceeded
5E 50 D0 0307 654 MOVL R0,SP : Allocate the space
030A 655
030A 656 :
030A 657 : Initialize the FAB and NAM blocks.
030A 658 :
030A 659
55 DD 030A 660 PUSHL R5 : Save R5 across MOVC
```

```
20 AE 00B0 8F 00 6E 00 2C 030C 661      MOVCS #0,(SP),#0,#<FAB$C_BLN+NAM$C_BLN>,FWA_FAB+4(SP) ; Clear FAB/NAM
      55 8ED0 0315 662      POPL R5 ; Restore R5
      52 1C AE 9E 0318 663      MOVAB FWA_FAB(SP),R2 ; Point to FAB
      53 50 A2 9E 031C 664      MOVAB FAB$C_BLN(R2),R3 ; Point to NAM
      62 34 A2 50 03 8F 80 0320 665      MOVW #<FAB$C_BID!<FAB$C_BLN@8>>,FAB$B_BID(R2) ; Set FAB identifier
      34 A2 55 90 0325 666      MOVW R5,FAB$B_FNS(R2) ; Set file name length
      2C A2 57 90 0329 667      MOVL R7,FAB$B_FNA(R2) ; Set file name address
      28 A2 63 9E 032D 668      MOVAB (R3),FAB$B_NAM(R2) ; Set NAM block address
      63 60 02 8F 80 0331 669      MOVW #<NAM$C_BID!<NAM$C_BLN@8>>,NAM$B_BID(R3) ; Set NAM identifier
      0A A3 FF 8F 90 0336 670      MOVW #NAM$C_MAXRSS,NAM$B_ESS(R3) ; Set ESA descriptor
      0C A3 00 CC CE 9E 033B 671      MOVAB FWA_ESA(SP),NAM$B_ESA(R3)
      56 27 9A 0341 672      MOVZBL #SJCS_FILE_IDENTIFICATION,R6 ; Set up item code
      57 14 A3 9E 0344 673      MOVAB NAM$B_DVI(R3),R7 ; Point to DVI/FID/DID area
      0348 674
      0348 675
      0348 676
      0348 677
      0348 678
      0348 679      $PARSE FAB=(R2) ; Parse the file name
      0C 50 E9 0351 680      BLBC R0,10$ ; Branch if error
      34 50 E8 0354 681      $SEARCH FAB=(R2) ; Search the file name
      0360 682      BLBS R0,50$ ; Branch to handle like FID item
      0360 683
      0360 684
      0360 685
      0360 686
      0360 687
      0223 31 0360 688 10$: BRW ERROR
      FDA1 31 0363 689 20$: BRW BADPARAM
      FDA3 31 0366 690 30$: BRW INSMEM
      0369 691
      0369 692
      0369 693 FILE_IDENTIFICATION: ; Translate SJCS_FILE_IDENTIFICATION
      0369 694
      0369 695
      0369 696
      0369 697
      0369 698
      0369 699
      0369 700
      0369 701
      0369 702
      0369 703
      0369 704
      0369 705
      0369 706
      0369 707
      036E 708
      0371 709
      0373 710
      02 16 EF 0375 711
      01 50 D1 037A 712
      037D 713
      FE 54 31 037F 714
      OF 67 91 0382 715 40$:
      DC 1A 0385 716      CMPB (R7),#15
      0387 717      BGTRU 20$ ; Branch if incorrect

      R5 = buffer size
      R6 = item code
      R7 = buffer address
      R10 = pointer to lowest available stack address

      Check that the parameter is the correct length. If it is not the expected
      28 bytes, and the previous mode is at least executive, assume that we have
      been passed the entire expanded item and send it on as is.

      TSTL FILE_ID(FP) ; See if there is already a filespec
      BNEQ 20$ ; Branch if so
      CMPW R5,#28 ; Ensure parameter is 28 bytes
      BEQL 40$ ; Branch if correct
      MOVPSL R0 ; Get PSL
      EXTZV #PSL$V_PRVMOD,#PSL$S_PRVMOD,R0,R0 ; Get previous mode
      CMPL R0,#PSL$C_EXEC ; Previous mode exec or kernel?
      BGTRU 20$ ; Branch if not
      BRW INPUT_ITEM ; Branch to store item as is
      CMPB (R7),#15 ; Ensure device no more than 15 bytes
      BGTRU 20$ ; Branch if incorrect
```



```
0387 718 :  
0387 719 : Check for sufficient space to allocate the work area, and do so.  
0387 720 :  
0387 721 :  
50 FE35 CE 9E 0387 722 : MOVAB -FWA_SIZE(SP),R0 : Get lowest address that will be used  
SA 50 D1 038C 723 : CMPL R0,R0 : Compare against that available  
05 1F 038F 724 : BLSSU 30$ : Branch if space exceeded  
5E 50 D0 0391 725 : MOVL R0,SP : Allocate the space  
0394 726 :  
0394 727 :  
0394 728 : Move the DVI/FID/DID to the work area.  
0394 729 :  
0394 730 :  
6E 67 1C 28 0394 731 50$: MOVCS #28,(R7),FWA_DVI(SP) : Move the parameter to the work area  
FC AD 5E D0 0398 732 : MOVL SP,FILE_ID(FP) : Save location of file ID buffer  
7E 56 3C 039C 733 : MOVZWL R6,-(SP) : Store item code, leave space for size  
FDC0 31 039F 734 : BRW ITEM : Remainder of processing comes later  
03A2 735 :  
03A2 736 :  
03A2 737 : The file specification, if any, must be post-processed after all items  
03A2 738 : have been digested. Inputs:  
03A2 739 :  
03A2 740 : R10 = address of file ID item  
03A2 741 :  
03A2 742 : Get a pointer to the DVI descriptor, and where the channel will be stored,  
03A2 743 : and initialize the descriptor.  
03A2 744 :  
03A2 745 :  
2C AA 0040 8F 00 6E 00 2C 03A2 746 POSTPROCESS_FID:  
03A2 747 : MOVCS #0,(SP),#0,#FIBSC_LENGTH,FWA_FIB(R10) : Initialize FIB  
D4 03AB 748 : CLRL 32(R10) : Clear unused longword  
50 20 AA D4 03AB 748 :  
53 24 AA 9E 03AE 749 : MOVAB FWA_DVI_DESC(R10),R0 : Point to DVI descriptor  
0144 CA 9E 03B2 750 : MOVAB FWA_CHAN(R10),R3 : Point to channel  
60 6A 9A 03B7 751 : MOVZBL FWA_DVI(R10),R0 : Store device name length  
04 A0 01 AA 9E 03BA 752 : MOVAB FWA_DVI+1(R10),4(R0) : Store device name address  
03BF 753 :  
03BF 754 :  
03BF 755 : Assign a channel to the device.  
03BF 756 :  
03BF 757 :  
03BF 758 : SASSIGN_S - : Assign a channel  
03BF 759 : DEVNAM=(R0), - : Device name  
03BF 760 : CHAN=(R3) : Output channel number  
91 50 E9 03CC 761 : BLBC R0,10$ : Branch if not assigned  
03CF 762 :  
03CF 763 :  
03CF 764 : Build the FIB, the FIB descriptor, and the ACP attributes list.  
03CF 765 :  
03CF 766 :  
50 6C AA 9E 03CF 767 : MOVAB FWA_ATRLIST(R10),R0 : Point to attribute list  
51 24 AA 9E 03D3 768 : MOVAB FWA_FIB_DESC(R10),R1 : Point to FIB descriptor  
52 0148 CA 9E 03D7 769 : MOVAB FWA_IOSB(R10),R2 : Point to IOSB  
54 2C AA 9E 03DC 770 : MOVAB FWA_FIB(R10),R4 : Point to FIB  
03E0 771 :  
04 A4 10 AA D0 03E0 772 : MOVL FWA_FID(R10),FIB$W_FID(R4) : Store file ID  
08 A4 14 AA B0 03E5 773 : MOVW FWA_FID+4(R10),FIB$W_FID+4(R4)  
18 F8 AD 00 E1 03EA 774 : BBC #DELETE_FLAG,FLAGS(FP),55$ : Branch if not deleting file
```

```
0A A4 16 AA D0 03EF 775      MOVL   FWA_DID(R10),FIBSW_DID(R4) ; Also store directory ID
OE A4 1A AA B0 03F4 776      MOVW   FWA_DID+4(R10),FIBSW_DID+4(R4)
14 A4 0800 8F A8 03F9 777      BISW   #FIBSM_FINDFID,FIBSW_NMCTL(R4)
      38 A4 01 C8 03FF 778      BISL   #FIBSM_ALT_REQ,FIBSL_STATUS(R4) ; Alternate access required
      3C A4 08 D0 0403 779      MOVL   #ARMSM_DELETE,FIBSL_ALT_ACCESS(R4) ; Check for delete access
      0407 780
61 00000040 8F D0 0407 781 55$: MOVL   #FIBSC_LENGTH,(R1) ; Initialize FIB descriptor
      04 A1 64 9E 040E 782      MOVAB  (R4),4(R1)
      0412 783
60 00040020 8F D0 0412 784      MOVL   #<ATR$S_RECATTR+<ATR$C_RECATTR@16>>,(R0)
04 A0 0124 CA 9E 0419 785      MOVAB  FWA_RECATTR(R10),4(R0)
08 A0 002E0100 8F D0 041F 786      MOVL   #<256+<ATR$C_FILE_SPEC@16>>,8(R0)
      0C A0 24 AA 9E 0427 787      MOVAB  FWA_FILE_SPEC(R10),12(R0)
      10 A0 D4 042C 788      CLRL   16(R0)
      042F 789
      042F 790 ; Access the file to get necessary information.
      042F 791 ;
      042F 792 ;
      042F 793 ;
      042F 794 ;
      042F 795 ;
      042F 796 ;
      042F 797 ;
      042F 798 ;
      042F 799 ;
      042F 800 ;
      50 DD 044D 801      PUSHL  R0 ; Issue QIO to obtain file attributes
      044F 802      $DASSGN_S - ; User's event flag
      044F 803      -CHAN=(R3) ; Channel number
      0459 804      POPL   R0 ; Read attributes function code
      045C 805      BLBC   R0,70$ ; I/O status block
      50 0148 CA 3C 045F 806      MOVZWL FWA_IOSB(R10),R0 ; Address of FIB descriptor
      40 50 E9 0464 807      BLBC   R0,70$ ; Address of attribute list
      0467 808 ; Save $QIOW status
      0467 809 ; Deassign the channel
      0467 810 ; Channel number
      0467 811 ; Restore status from access
      0467 812 ; Branch if $QIOW failed
      046E 813      ROTL   #16, - ; Move EFBLK to file size area and
      046E 814      FWA_RECATTR+FAT$E_FBLK(R10), - ; convert to unswapped
      046E 815      FWA_FILE_SIZE(R10) ; Branch if EFBLK is zero
      09 13 046E 816      BEQL   60$ ; Branch if EFBLK is zero
      0130 CA B5 0470 817      TSTW   FWA_RECATTR+FAT$W_FFBYTE(R10) ; Test first free byte
      03 12 0474 818      BNEQ   60$ ; Branch if nonzero
      1C AA D7 0476 819      DECL   FWA_FILE_SIZE(R10) ; Adjust EFBLK
      0479 820 ;
      0479 821 ; Slide the real data up adjacent to the previous item on the stack, and
      0479 822 ; finish it by adding the length and item code.
      0479 823 ;
      0479 824 ;
      0479 825 ;
      57 24 AA 3C 0479 826 60$: MOVZWL FWA_FILE_SPEC(R10),R7 ; Get file specification length
00FE 8F 57 B1 047D 827      CMPW   R7,#254 ; Check against maximum supported length
      05 1B 0482 828      BLEQU  65$ ; Branch if in range
      57 00FE 8F 3C 0484 829      MOVZWL #254,R7 ; Shorten to maximum
      57 26 C0 0489 830 65$: ADDL   #FWA_FILE_SPEC+2,R7 ; Add fixed portion
      FE AA 57 B0 048C 831      MOVW   R7,-2(R10) ; Store length in message
```

SYSSNDJBC  
V04-000

G 12  
- SEND MESSAGE TO JOB CONTROLLER  
EXE\$SNDJBC - Send message to job control

16-SEP-1984 02:34:54 VAX/VMS Macro V04-00  
5-SEP-1984 03:57:37 [SYS.SRC]SYSSNDJBC.MAR;1

Page 17  
(7)

```
58 000001CB 8F 57 C3 0490 832 SUBL3 R7,#FWA_SIZE,R8 ; Compute bias
      57 5A C0 0498 833 ADDL R10,R7 ; Compute size of area above filespec
      57 5E C2 049B 834 SUBL SP,R7 ; = R10 - SP + R7
      6E48 6E 57 28 049E 835 MOVCL R7,(SP),(SP)[R8] ; Squish out unused space
      SE 5B C0 04A3 836 ADDL R8,SP ; Delete unused stack
      OS 05 04A6 837 RSB ; Done with file spec
      04A7 838
      04A7 839 ;
      04A7 840 ; Helper branches.
      04A7 841 ;
      04A7 842 ;
      00DC 31 04A7 843 70$: BRW ERROR
      04AA 844
      04AA 845 .DSABL LSB
```

SYS  
V04



```
04AA 847
04AA 848
04AA 849 : Stack work area offsets for next routine.
04AA 850
04AA 851
00000000 04AA 852 LWA_BUFFER= 0 : Logical name buffer
00000100 04AA 853 LWA_LOGNAM= 256 : Logical name descriptor
00000108 04AA 854 LWA_ITMLST= 264 : $TRNLNM item list
00000124 04AA 855 LWA_RSLLEN= 292 : Translation length buffer
00000128 04AA 856 LWA_ATTRBUF= 296 : Translation attributes buffer
0000012C 04AA 857 LWA_SIZE= 300 : Work area length
04AA 858
04AA 859 .ENABL LSB
FC5A 31 04AA 860 10$: BRW BADPARAM
FC5C 31 04AD 861 20$: BRW INSFMEM
04B0 862
04B0 863 TRANSLATE_OBJECT: : Translate object names
04B0 864
04B0 865 :
04B0 866 : R5 = buffer size
04B0 867 : R6 = item code
04B0 868 : R7 = buffer address
04B0 869 : R10 = pointer to lowest available stack address
04B0 870
04B0 871 : Check that the parameter is the correct length and that there is sufficient
04B0 872 : space to allocate the work area (then do so).
04B0 873
04B0 874
00FF 8F 55 B1 04B0 875 CMPW R5,#255 : Ensure no more than 255 bytes
F3 1A 04B5 876 BGTRU 10$ : Branch if incorrect
04B7 877
53 FED4 CE 9E 04B7 878 MOVAB -LWA_SIZE(SP),R3 : Get lowest address that will be used
5A 53 D1 04BC 879 CMPL R3,R10 : Compare against that available
EC 1F 04BF 880 BLSSU 20$ : Branch if space exceeded
5E 53 D0 04C1 881 MOVL R3,SP : Allocate the space
04C4 882
04C4 883 :
04C4 884 : Prepare to perform the iterative translations by initializing the logical name
04C4 885 : descriptor and the item list utilized by the recursive $TRNLNMs.
04C4 886
04C4 887
63 67 55 DD 04C4 888 PUSHL R5 : Save the input string length
55 28 04C6 889 MOVCL R5,(R7),(R3) : Move input string into scratch buffer
55 8ED0 04CA 890 POPL R5 : Restore the input string length
57 5E D0 04CD 891 MOVL SP,R7 : Restore scratch buffer address
04D0 892
51 0104 C7 9E 04D0 893 MOVAB LWA_LOGNAM+4(R7),R1 : Addr of area requiring initialization
81 67 9E 04D5 894 MOVAB (R7),(R1)+ : Init log name descriptor buffer addr
04D8 895
81 000200FF 8F D0 04D8 896 MOVL #<LNMS STRING @ 16+- : Init string item list item type
04DF 897 255>,(R1)+ : and string buffer length
04DF 898 MOVAB (R7),(R1)+ : Init string item buffer address
81 0124 C7 9E 04E2 899 MOVAB LWA_RSLLEN(R7),(R1)+ : Init string item return buffer address
81 00030004 8F D0 04E7 900 MOVL #<LNMS ATTRIBUTES @ 16+- : Init attributes item list item type
04EE 901 4>,(R1)+ : and attributes buffer length
81 0128 C7 9E 04EE 902 MOVAB LWA_ATTRBUF(R7),(R1)+ : Init attributes item buffer address
61 7C 04F3 903 CLRQ (R1) : Init attributes item return buffer
```

			04F5	904		; address and end of item list marker
			04F5	905		
54	OA	D0	04F5	906	MOVL	#LNMSC_MAXDEPTH,R4 ; Initialize loop counter

SY5  
V04

04  
00'  
02  
00

```
04F8 908
04F8 909
04F8 910 : Loop to iterate over translations.
04F8 911
04F8 912 R4 = Current translation count
04F8 913 R5 = Current input string length
04F8 914 R6 = Item code
04F8 915 R7 = Current input string address, and
04F8 916 Address of work area
04F8 917
04F8 918 : The iterations successfully terminate when:
04F8 919
04F8 920 1. The maximum translation recursion depth is exceeded.
04F8 921 2. The current translation succeeds but the translation is marked terminal.
04F8 922 3. The current translation fails with an error of SSS_NOLOGNAM.
04F8 923
04F8 924 : The iterations unsuccessfully terminate when:
04F8 925
04F8 926 1. The current translation fails with some error other than SSS_NOLOGNAM.
04F8 927 2. The current translation exceeds but the equivalence string is either of
04F8 928 null length or does not exist.
04F8 929
04F8 930
0100 C7 55 D0 04F8 931 30$: MOVL R5,LWA_LOGNAM(R7) : Store name length in descriptor
04FD 932
04FD 933 STRNLNM_S = : Attempt to translate the name
04FD 934 ATTR = TRNLNM_ATTR,- : Case-insensitive translation
04FD 935 ITMLST = LWA_ITMLST(R7),- : Address of item list
04FD 936 LOGNAM = LWA_LOGNAM(R7),- : Address of name descriptor
04FD 937 TABNAM = TRNENM_TABLE : Addr LNMSFILE_DEV descriptor
19 50 E9 0516 938 BLBC R0,45$ : Done if translation fails
0519 939
55 0124 C7 3C 0519 940 MOVZWL LWA_RSLLEN(R7),R5 : Retrieve length of equivalence string
0B 13 051E 941 BEQL 40$ : Go return error if length is 0
0520 942 : (null or non-existent translation)
0520 943
13 0128 09 20 0520 944 BBS #LNMSV TERMINAL,- : Is the translation marked terminal?
C7 0522 945 LWA_ATTRBUF(R7),50$ : terminate iterative translations if so
CF 54 F5 0526 946 SOBGTR R4,30$ : Continue if more translations possible
DE 11 0529 947 BRB 50$ : Else, done if xlation count exhausted
052B 948
50 0154 8F 3C 052B 949 40$: MOVZWL #SS$_IVLOGNAM,R0 : Return an error for null length or
54 11 0530 950 BRB ERROR : non-existent translation
0532 951
01BC 8F 50 B1 0532 952 45$: CMPW R0,#SS$_NOLOGNAM : If the translation failed for a reason
4D 12 0537 953 BNEQ ERROR : other than the logical name did not
0539 954 : exist then go return the error
```



```
0539 956
0539 957
0539 958 : Recursive translations have completed. Format the final translation by
0539 959 : removing blanks, tabs, null characters, and a trailing colon if there is one,
0539 960 : and upcasing the name using the DEC multi-national character upcasing table.
0539 961
0539 962 : R1 = Current character
0539 963 : R2 = Current character index
0539 964 : R3 = Cursor to output buffer
0539 965 : R5 = Length of input string
0539 966 : R7 = Address of input string
0539 967
0539 968
0539 969 50$: MNEGL #1,R2 : Initialize the loop index
52 01 CE 0539 970 : MOVL R7,R3 : Initialize output buffer cursor
53 57 DO 053C 971 : BRB 70$ : Branch to enter the loop
18 11 053F 972
0541 973
51 6742 9A 0541 973 60$: MOVZBL (R7)[R2],R1 : Pick up the current character
12 13 0545 974 : BEQL 70$ : Remove it if it is null
20 51 91 0547 975 : CMPB R1,#^A' : Is the current character a blank?
0D 13 054A 976 : BEQL 70$ : Remove it if it is
09 51 91 054C 977 : CMPB R1,#^0011 : Is the current character a tab?
08 13 054F 978 : BEQL 70$ : Remove it if it is
83 00000000'GF41 90 0551 979 : MOVB G^EXE$UPCASE_DAT[R1],- : Move upcased character into output
0559 980 : (R3)+ : buffer
E4 52 55 F2 0559 981 70$: AOBLS R5,R2,60$ : Continue loop until done
055D 982
57 53 57 C3 055D 983 : SUBL3 R7,R3,R7 : Computes name's compressed length
C8 13 0561 984 : BEQL 40$ : Return an error if its zero
3A FF A3 91 0563 985 : CMPB -1(R3),#^A': : Is there a trailing colon?
04 12 0567 986 : BNEQ 80$ : Branch if there isn't
57 D7 0569 987 : DECL R7 : Otherwise remove it
BE 13 056B 988 : BEQL 40$ : Return an error if name length is 0
056D 989
056D 990
056D 991 : Slide the name up the stack so that it is adjacent to the previous item on
056D 992 : the stack. Then complete the formation of the item by adding the name length
056D 993 : and item code.
056D 994
056D 995
58 0000012C 8F 57 C3 056D 996 80$: SUBL3 R7,#LWA SIZE,R8 : Compute bias
6E 57 28 0575 997 : MOVC3 R7,(SP),-(SP)[R8] : Slide item up
5E 58 C0 057A 998 : ADDL2 R8,SP : Delete unused stack
7E 57 B0 057D 999 : MOVW R7,-(SP) : Store item length
7E 56 B0 0580 1000 : MOVW R6,-(SP) : Store item code
FBDC 31 0583 1001 : BRW ITEM : Return to item list processing
0586 1002 : .DSABL LSB
```

```
0586 1004
0586 1005
0586 1006 : Synchronous error return path. Store status in the IOSB, set the event flag,
0586 1007 : and declare the AST, if specified.
0586 1008
0586 1009
00000000'GF 50 DD 0586 1010 ERROR: PUSHL R0 : Save completion status
51 14 AC 6C FA 0588 1011 CALLG (AP),G^SYSS$SETEF : Set specified event flag
09 13 DO 058F 1012 MOVL IOSB(AP),R1 : Get address of IOSB
0593 1013 BEQL 10$ : Branch if none
0595 1014 IFNOWRT #8,(R1),10$ : Branch if no write access
51 61 6E DO 059B 1015 MOVL (SP),(R1) : Store completion status
18 AC DO 059E 1016 10$: MOVL ASTADR(AP),R1 : Get address of AST routine
15 13 05A2 1017 BEQL 20$ : Branch if none
50 50 02 16 DC 05A4 1018 MOVPSL R0 : Get PSL
50 8ED0 05A6 1019 EXTZV #PSLSV_PVMOD,#PSLSS_PVMOD,R0,R0 : Get previous mode
04 05AB 1020 $DCLAST_S (R1),ASTPRM(AP),R0 : Declare completion AST
05B9 1021 20$: POPL R0 : Restore completion status
05BC 1022 RET : Return with error status
```

```
05BD 1024      .SBTTL EXE$JBCRSP - Store response from job controller
05BD 1025
05BD 1026      ++
05BD 1027
05BD 1028      EXE$JBCRSP - STORE RESPONSE FROM JOB CONTROLLER
05BD 1029
05BD 1030      FUNCTIONAL DESCRIPTION:
05BD 1031
05BD 1032      This routine is called as a special kernel AST routine to return status
05BD 1033      from the send to job controller system service to the requesting
05BD 1034      process. It ensures that the same image is executing and then sets the
05BD 1035      specified event flag, stores a status value in the IOSB if specified,
05BD 1036      stores data in any output buffer items that were in the original
05BD 1037      request, and declares the completion AST if specified. If appropriate,
05BD 1038      the ACB is deallocated.
05BD 1039
05BD 1040      INPUTS:
05BD 1041      R0-R3      = scratch
05BD 1042      R4          = PCB address
05BD 1043      R5          = ACB address
05BD 1044
05BD 1045      OUTPUTS:
05BD 1046      See above.
05BD 1047      --
05BD 1048
05BD 1049      EXE$JBCRSP::                                : Response from job controller
05BD 1050
05BD 1051      :
05BD 1052      : Compare the image count when the request was queued with the current image
05BD 1053      : count. If different, a new image is running - do not store anything.
05BD 1054      :
05BD 1055
05BD 1056      MOVL      @#CTL$GL PHD,R3                      : Get PHD address
05BD 1057      CML      PHD$L_IMGCNT(R3),ACB_L_IMGCNT(R5)      : See if image count correct
05BD 1058      BEQL      10$                                     : Branch if correct
05BD 1059      BRW       70$                                     : Join code to deallocate ACB
05BD 1060
05BD 1061      :
05BD 1062      : Loop over the return item descriptors storing information in the user's
05BD 1063      : output buffers. During this loop:
05BD 1064      :
05BD 1065      : R5 = user buffer address
05BD 1066      : R6 = pointer to item descriptors in ACB
05BD 1067      : R7 = user buffer size
05BD 1068      : R8 = actual data size
05BD 1069      : R9 = requester's access mode
05BD 1070      : R10 = item count
05BD 1071      :
05BD 1072
05BD 1073      10$:      TSTW      ACB_W_ITEMCOUNT(R5)          : Any items to return?
05BD 1074      BEQL      50$                                     : Branch if none
05BD 1075      PUSHR     #^M<R4,R5,R6,R7,R8,R9,R10>             : Save registers
05BD 1076      MOVAB     ACB_B_ITEMS(R5),R6                    : Point to items
05BD 1077      MOVZBL     ACB$B_RMOD(R5),R9                     : Get requester's mode
05BD 1078      MOVZWL     ACB_W_ITEMCOUNT(R5),R10              : Get item count
05BD 1079      20$:      MOVZWL     (R6)+,R7                     : Get user buffer size
05BD 1080      MOVZWL     (R6)+,R8                               : Get actual size
```

53 00000000'9F D0 05BD 1056  
1C A5 00F4 C3 D1 05C4 1057  
03 13 05CA 1058  
0085 31 05CC 1059  
05CF 1060  
05CF 1061  
05CF 1062  
05CF 1063  
05CF 1064  
05CF 1065  
05CF 1066  
05CF 1067  
05CF 1068  
05CF 1069  
05CF 1070  
05CF 1071  
05CF 1072  
2C A5 B5 05CF 1073  
52 13 05D2 1074  
07F0 8F BB 05D4 1075  
56 2E A5 9E 05D8 1076  
59 0B A5 9A 05DC 1077  
5A 2C A5 3C 05E0 1078  
57 86 3C 05E4 1079  
58 86 3C 05E7 1080



```

        55 86 D0 05EA 1081      MOVL (R6)+,R5      ; Get data buffer address
        50 55 D0 05ED 1082      MOVL R5,R0        ; R0 = buffer address
        51 57 D0 05F0 1083      MOVL R7,R1        ; R1 = buffer length
        53 59 D0 05F3 1084      MOVL R9,R3        ; R3 = requester's mode
00000000'EF 16 05F6 1085      JSB EXE$PROBEW      ; Probe for write access
        66 50 E9 05FC 1086      BLBC R0,90$      ; Branch if inaccessible
65 57 00 04 A6 58 2C 05FF 1087      MOVCS R8,4(R6),#0,R7,(R5) ; Move data to user buffer
        55 86 D0 0606 1088      MOVL (R6)+,R5      ; Get return length address
        11 13 0609 1089      BEQL 40$          ; Branch if none
        060B 1090      IFNOWRT #2,(R5),90$,R9      ; Probe for write access
        57 58 D1 0611 1091      CMPL R8,R7        ; Minimize user and actual length
        03 1E 0614 1092      BGEQU 30$         ; Branch if actual length larger
        57 58 D0 0616 1093      MOVL R8,R7        ; Get actual length as minimum
        65 57 B0 0619 1094 30$: MOVW R7,(R5)      ; Return buffer length
        56 58 C0 061C 1095 40$: ADDL2 R8,R6      ; Advance over data
        C2 5A F5 061F 1096      SOBGTR R10,20$   ; Loop for all items
07F0 8F BA 0622 1097      POPR #*M<R4,R5,R6,R7,R8,R9,R10> ; Restore registers
        0626 1098
        0626 1099
        0626 1100      ; Output buffers stored. Set the specified event flag, return status to the
        0626 1101      ; IOSB, and declare the completion AST if specified. If no AST specified,
        0626 1102      ; deallocate the ACB.
        0626 1103
        0626 1104
        51 60 A4 D0 0626 1105 50$: MOVL PCB$ _PID(R4),R1 ; R1 = PID
        53 52 D4 062A 1106      CLRL R2          ; R2 = null priority increment
00000000'EF 16 062C 1107      MOVZBL ACB _L_EFN(R5),R3 ; R3 = event flag number
        51 24 A5 D0 0630 1108      JSB SCH$POSTEF ; Set specified event flag
        0B 13 063A 1109      MOVL ACB _L_IOSB(R5),R1 ; Get IOSB address
        61 28 A5 D0 063C 1110      BEQL 60$      ; Branch if none
        10 A5 D5 0643 1111      IFNOWRT #4,(R1),60$,ACB$_RMOD(R5) ; Probe for write access
        08 13 0647 1112      MOVL ACB _L_STATUS(R5),R1 ; Return status
00000000'EF 17 064A 1113 60$: TSTL ACB$_AST(R5) ; Completion AST specified?
        52 D4 064C 1114      BEQL 70$          ; Branch if no to deallocate ACB
        00000000'EF 17 064E 1115      CLRL R2    ; R2 = null priority increment
        0654 1116      JMP SCH$_AST           ; Queue completion AST and return
        0654 1117
        0654 1118
        0654 1119      ; Processing finished. Return AST quota if charged, and deallocate the ACB.
        0654 1120      ; (No byte count quota is charged for this ACB because it is allocated by the
        0654 1121      ; job controller.)
        0654 1122
        0654 1123
        03 0B A5 06 E1 0654 1124 70$: BBC #ACB$_QUOTA,ACB$_RMOD(R5),80$ ; Branch if no AST quota charged
        38 A4 B6 0659 1125      INCW PCB$_ASTCNT(R4) ; Return AST quota
        50 55 D0 065C 1126 80$: MOVL R5,R0      ; R0 = ACB address
        00000000'EF 17 065F 1127      JMP EXE$DEANONPAGED ; Deallocate ACB and return
        0665 1128
        0665 1129
        0665 1130      ; Memory is inaccessible. Attempt to return an access violation status to
        0665 1131      ; the IOSB.
        0665 1132
        0665 1133
        07F0 8F BA 0665 1134 90$: POPR #*M<R4,R5,R6,R7,R8,R9,R10> ; Restore registers
        28 A5 0C D0 0669 1135      MOVL #SS$_ACCVIO,ACB _L_STATUS(R5) ; Force status to ACCVIO
        B7 11 066D 1136      BRB 50$          ; Go to return EFN and IOSB
        066F 1137      .END
```

SYSSNDJBC  
Symbol table

- SEND MESSAGE TO JOB CONTROLLER

B 13

16-SEP-1984 02:34:54 VAX/VMS Macro V04-00  
5-SEP-1984 03:57:37 [SYS.SRC]SYSSNDJBC.MAR;1Page 25  
(16)SYS  
V04

\$\$TMP1	=	00000001		
\$\$TMP2	=	00000062		
\$\$T1	=	00000000		
ACBSB_RMOD	=	0000000B		
ACBSL_AST	=	00000010		
ACBSL_KAST	=	00000018		
ACBSV_QUOTA	=	00000006		
ACB_B_ITEMS	=	0000002E		
ACB_L_EFN	=	00000020		
ACB_L_IMGCNT	=	0000001C		
ACB_L_IOSB	=	00000024		
ACB_L_STATUS	=	00000028		
ACB_W_ITEMCOUNT	=	0000002C		
ACCVIO	=	00000102	R	02
ACMSQ_SYSTIME	=	0000003C		
ARMSM_DELETE	=	00000008		
ASTADR	=	00000018		
ASTPRM	=	0000001C		
ATRSC_FILE_SPEC	=	0000002E		
ATRSC_RECATTR	=	00000004		
ATRSS_RECATTR	=	00000020		
BADPARAM	=	00000107	R	02
BOOL_ITEM	=	0000000C		
CTLSAL_STACKLIM	*****		X	02
CTLSGL_PCB	*****		X	02
CTLSGL_PHD	*****		X	02
CTLST_USERNAME	*****		X	02
DELETE_FLAG	=	00000000		
EFN	=	00000004		
ERROR	=	00000586	R	02
EXESDEANONPAGED	*****		X	02
EXESGETQUI	=	00000114	RG	02
EXESGQ_SYSTIME	*****		X	02
EXESJBCRSP	=	0000058D	RG	02
EXESPROBER	*****		X	02
EXESPROBEW	*****		X	02
EXESSENDMSG	*****		X	02
EXESSNDJBC	=	0000011C	RG	02
EXESUPCASE_DAT	*****		X	02
FABSB_BID	=	00000000		
FABSB_FNS	=	00000034		
FABSC_BID	=	00000003		
FABSC_BLN	=	00000050		
FABSL_FNA	=	0000002C		
FABSL_NAM	=	00000028		
FATSL_EFBLK	=	00000008		
FATSW_FFBYTE	=	0000000C		
FIBSC_LENGTH	=	00000040		
FIBSL_ALT_ACCESS	=	0000003C		
FIBSL_STATUS	=	00000038		
FIBSM_ALT_REQ	=	00000001		
FIBSM_FINDFID	=	00000800		
FIBSW_DID	=	0000000A		
FIBSW_FID	=	00000004		
FIBSW_NMCTL	=	00000014		
FILE_ID	=	FFFFFFFFC		
FILE_IDENTIFICATION	=	00000369	R	02

FILE_SPECIFICATION	=	000002F1	R	02
FINISH_MESSAGE	=	0000021D	R	02
FIXED_AREA	=	0000005A		
FLAGS	=	FFFFFFFF8		
FUNC	=	00000008		
FWA_ATRLIST	=	0000006C		
FWA_CHAN	=	00000144		
FWA_DID	=	00000016		
FWA_DVI	=	00000000		
FWA_DVI_DESC	=	00000024		
FWA_ESA	=	000000CC		
FWA_FAB	=	0000001C		
FWA_FIB	=	0000002C		
FWA_FIB_DESC	=	00000024		
FWA_FID	=	00000010		
FWA_FILE_SIZE	=	0000001C		
FWA_FILE_SPEC	=	00000024		
FWA_IOSB	=	00000148		
FWA_NAM	=	0000006C		
FWA_RECATTR	=	00000124		
FWA_SIZE	=	000001CB		
GETQUI_BOOL_ITEM	=	00000020	R	02
GETQUI_DATA	=	000000D2	R	02
GETQUI_OUTPUT_ITEM	=	00000060	R	02
GETQUI_SPECIAL_TABLE	=	000000B2	R	02
INPUT_ITEM	=	000001D6	R	02
INSMEM	=	0000010C	R	02
IOS ACCESS	=	00000032		
IOSB	=	00000014		
ITEM	=	00000162	R	02
ITMLST	=	00000010		
LNMSC_MAXDEPTH	=	0000000A		
LNMSM_CASE_BLIND	=	02000000		
LNMSV_TERMINAL	=	00000009		
LNMS_ATTRIBUTES	=	00000003		
LNMS_STRING	=	00000002		
LWA_ATTRBUF	=	00000128		
LWA_BUFFER	=	00000000		
LWA_ITMLST	=	00000108		
LWA_LOGNAM	=	00000100		
LWA_RSLEN	=	00000124		
LWA_SIZE	=	0000012C		
MAX_FUNC	=	00000004		
MAX_ITEM	=	00000008		
MSG\$GETQUI	=	00000010		
MSG\$SNDJBC	=	0000000F		
MSG CODE	=	00000000		
NAM\$B_BID	=	00000000		
NAM\$B_ESS	=	0000000A		
NAM\$C_BID	=	00000002		
NAM\$C_BLN	=	00000060		
NAM\$C_MAXRSS	=	000000FF		
NAM\$E_ESA	=	0000000C		
NAM\$T_DVI	=	00000014		
NULARG	=	0000000C		
OUTPUT_ITEM	=	00000010		
PCBSB_Prib	=	0000002F		



SYSSNDJBC  
Symbol table

- SEND MESSAGE TO JOB CONTROLLER C 13

16-SEP-1984 02:34:54 VAX/VMS Macro V04-00  
5-SEP-1984 03:57:37 [SYS.SRC]SYSSNDJBC.MAR;1Page 26  
(16)

PCBSL_EOWNER	=	00000068		
PCBSL_EPID	=	00000064		
PCBSL_PID	=	00000060		
PCBSL_STS	=	00000024		
PCBSL_UIC	=	000000BC		
PCBST_TERMINAL	=	00000044		
PCBSW_ASTCNT	=	00000038		
PHDSL_IMGCNT	=	000000F4		
PHDSQ_PRIVMSK	=	00000000		
POSTPROCESS_FID	=	000003A2	R	02
PSLSC_EXEC	=	00000001		
PSLSS_CURMOD	=	00000002		
PSLSS_PRVMOD	=	00000002		
PSLSV_CURMOD	=	00000018		
PSLSV_PRVMOD	=	00000016		
QUIS_RESERVED_FUNC_2	=	00000009		
QUIS_RESERVED_OUTPUT_6	=	0000005E		
QUIS_SEARCH_NAME	=	0000004D		
SCH\$CLREF	*****		X	02
SCH\$POSTEF	*****		X	02
SCH\$QAST	*****		X	02
SJCS_CHARACTERISTIC_NAME	=	0000000C		
SJCS_DELETE_FILE	=	00C00018		
SJCS_DESTINATION_QUEUE	=	0000001A		
SJCS_FILE_IDENTIFICATION	=	00000027		
SJCS_FILE_SPECIFICATION	=	0000002A		
SJCS_FORM_NAME	=	00000036		
SJCS_GENERIC_TARGET	=	00000046		
SJCS_LOG_QUEUE	=	00000061		
SJCS_QUEUE	=	00000086		
SJCS_RESERVED_FUNC_2	=	00000020		
SJCS_RESERVED_OUTPUT_2	=	000000AB		
SNDJBC_BOOL_ITEM	=	00000000	R	02
SNDJBC_DATA	=	000000EA	R	02
SNDJBC_OUTPUT_ITEM	=	00000040	R	02
SNDJBC_SPECIAL_TABLE	=	00000080	R	02
SPECIAL_TABLE	=	00000014		
SS\$ACCVIO	=	0000000C		
SS\$BADPARAM	=	00000014		
SS\$EXASTLM	=	00002A04		
SS\$INSFMEM	=	00000124		
SS\$IVLOGNAM	=	00000154		
SS\$NOLOGNAM	=	000001BC		
SYSS\$ASSIGN	*****		GX	02
SYSS\$CMKRNL	*****		GX	02
SYSS\$DASSGN	*****		GX	02
SYSS\$DCLAST	*****		GX	02
SYSS\$GL_JOBCTLMB	*****		X	02
SYSS\$PARSE	*****		GX	02
SYSS\$QIOW	*****		GX	02
SYSS\$SEARCH	*****		GX	02
SYSS\$SETEF	*****		X	02
SYSS\$TRNLNM	*****		GX	02
TRANSLATE_OBJECT	=	000004B0	R	02
TRNLNM_ATTR	=	000000BA	R	02
TRNLNM_TABLE	=	000000BE	R	02

SYS  
V04



+-----+  
! Psect synopsis !  
+-----+

PSECT name	Allocation	PSECT No.	Attributes
ABS	00000000 ( 0.)	00 ( 0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
\$ABSS	0000002E ( 46.)	01 ( 1.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE
Y\$EXEPAGED	0000066F ( 1647.)	02 ( 2.)	NOPIC USR CON REL LCL NOSHR EXE RD WRT NOVEC BYTE

+-----+  
! Performance indicators !  
+-----+

Phase	Page faults	CPU Time	Elapsed Time
Initialization	29	00:00:00.08	00:00:00.26
Command processing	110	00:00:00.54	00:00:01.22
Pass 1	566	00:00:23.66	00:00:27.07
Symbol table sort	0	00:00:03.96	00:00:04.13
Pass 2	208	00:00:04.77	00:00:05.38
Symbol table output	20	00:00:00.18	00:00:00.20
Psect synopsis output	3	00:00:00.03	00:00:00.03
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	938	00:00:33.22	00:00:38.29

The working set limit was 1800 pages.  
135859 bytes (266 pages) of virtual memory were used to buffer the intermediate code.  
There were 140 pages of symbol table space allocated to hold 2520 non-local and 48 local symbols.  
1137 source lines were read in Pass 1, producing 17 object records in Pass 2.  
40 pages of virtual memory were used to define 38 macros.

+-----+  
! Macro library statistics !  
+-----+

Macro library name	Macros defined
\$255\$DUA28:[SYS.OBJ]LIB.MLB;1	7
\$255\$DUA28:[SYSLIB]STARLET.MLB;2	28
TOTALS (all libraries)	35

2706 GETS were required to define 35 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS\$:SYSSNDJBC/OBJ=OBJ\$:SYSSNDJBC MSRC\$:SYSSNDJBC/UPDATE=(ENH\$:SYSSNDJBC)+EXECML\$/LIB



AH-BT13A-SE  
 VAX/VMS V4.0

DIGITAL EQUIPMENT CORPORATION  
CONFIDENTIAL AND PROPRIETARY